

CHANGING FORM, FONT, AND FCB ID'S DURING TRANSMISSION

Remote SpoolPrint3X/400 will optionally translate Forms ID's and Font ID's and S/370 FCB Names during transmission to the remote system. This feature is useful when the source and target systems have different Forms ID naming conventions. The translation can be different for each remote writer. For example the forms ID 'CHK9' can be translated to 'CHECK9I' when transmitted to Remote System A, and translated to 'CK9I' when transmitted to Remote System B. A forms translation table is used to define the translation scheme.

Before a Remote Writer transmits a spool entry, the entry's Forms ID is checked in the table. First Remote SpoolPrint3X/400 checks for a table entry which matches both the Forms ID and the Remote Writer name. If a match is found, the Forms ID is changed. If no match is found, the table is checked for an entry which matches the Forms ID and has *ANY for the Remote Writer Name. If a match is found, the forms ID is changed. If no match is found, no translation takes place. The Remote Writer translates Font ID's and FCB Names using the same algorithm.

Managing the Forms Translation Table

To enter, update, or delete forms translation entries, use the command **MNGRMFCT**. The following screen should appear:

```
Prg:RS30                      Remote SpoolPrint/3X                      Mode:XXXX
                               Maintain the Forms Translate Table

                               Source Forms ID: _____
                               Remote Writer Name: _____ or *ANY
                               Target Forms ID: _____

                               Text: _____

                               CMD3=Prior Selection  CMD4=Delete  Cmd7=Exit
```

The MNGRMFCT command has the following parameters:

Source Forms ID

Specifies the Forms ID on the source system which is to be translated when encountered.

Remote Writer Name

Specifies the Remote Writer name. Both the Forms ID and Remote Writer name are used to test for translation. A value of *ANY specifies that any remote writer will use this entry for translation.

Target Forms ID

REMOTE SPOOLPRINT 3X/400™

Specifies the Forms ID to substitute. Please note that the System/36 Forms ID must be no longer than 4 characters. The remaining characters will be truncated.

Text

Specify descriptive text.

Listing the Forms Translation Table

Use the LSTRMFCT command to list Forms Translation Table entries.

Managing the Font Translation Table

To enter, update, or delete font translation entries, use the command MNGFONT. The following screen should appear:

```
Prg:RS32                               Remote SpoolPrint/3X                               Mode:XXXX
                                         Maintain the Font Translate Table

                                         Source Font ID:_____
Remote Writer Name:_____              or   *ANY

                                         Target Font ID:_____
                                         Text:_____

CMD3=Prior Selection    CMD4=Delete    Cmd7=Exit
```

The MNGFONT command has the following parameters:

Source Font ID

Specifies the Font ID on the source system which is to be translated when encountered.

Remote Writer Name

Specifies the Remote Writer name. Both the Font ID and Remote Writer name are used to test for translation. A value of *ANY specifies that any remote writer will use this entry for translation.

Target Font ID

Specifies the Font ID to substitute. Please note that the System/36 Font ID must be 2 hex characters.

Text

Specify descriptive text.

Listing the Font Translation Table

CHANGING FORM, FONT, AND FCB ID'S DURING TRANSMISSION

Use the LSTFONT command to list Font Translation Table entries.

Managing the FCB Translation Table

To enter, update, or delete S/370 FCB translation entries, use the command MNGFCB. The following screen should appear:

```
Prg:RS34                      Remote SpoolPrint/36                      Mode:XXXX
                                Maintain the S/370 FCB Translate Table

                                Remote Writer Name:_____ or *ANY
                                Source Lines per Page:_____
                                Source Lines per Inch:_____
                                Target FCB Name:_____
                                Text:_____

                                CMD3=Prior Selection    CMD4=Delete    Cmd7=Exit
```

The MNGFCB command has the following parameters:

Remote Writer Name

Specifies the Remote Writer name. The Remote Writer name, Lines per Inch, and Lines per Page values are used to test for translation. A value of *ANY specifies that any remote writer will use this entry for translation.

Source Lines per Page

Specifies the Lines per Page attribute to use for translation.

Source Lines per Inch

Specifies the Lines per Inch attribute to use for translation.

Target FCB Name

Specifies the FCB Name to substitute. Please note that the FCB Name must exist on the remote system.

Text

Specify descriptive text.

Listing the FCB Translation Table

Use the LSTFCB command to list S/370 FCB Translation Table entries.