

REMOTE SPOOLPRINT/38/400 MAIN MENUS

AS/400

To display the Remote SpoolPrint/400 main menu, enter the following command at the command line:

GO BRODERICK/RSPL

Note: If the Remote SpoolPrint product library (BRODERICK) is located in an Independent ASP, the user must set the IASP prior to issuing Remote SpoolPrint commands. For more information, refer to Appendix J, ASP Considerations.

Then press enter and the following screen should appear:

```
RSPL                               Remote SpoolPrint/400 Main Menu™   3/22/96   11:47:48

  Remote Writer Control                               Remote Writer Definition

1. Start Remote Writer (STRMWTR)                       11. Manage Remote Writers (MNGRMWTR)
2. Cancel Remote Writer (CNLRMWTR)                     12. List Remote Writers (LSTRMWTR)
3. Display Writer Status(DSPRMSTS)                     13. Tailoring Options (BRSPLSETUP)
4. Start TCP Server (STRMSVR)
5. End TCP Server (ENDRMSVR)

  Translation Table Management                       Other Functions

21. Manage Forms Table (MNGFRMTBL)                    31. Dwnld S/36 TOLIBR Img (S36DOWNL)
22. List Forms Table (LSTFRMTBL)                      32. Dwnld S/36 Folder Img (S36DOWNF)
23. Manage Font Table (MNGFONTBL)                    33. Display RSPL Log (DSPRSLOG)
24. List Font Table (LSTFONTBL)
25. Manage S/370 FCB Tbl(MNGFCBTBL)
26. List S/370 FCB Tbl (LSTFCBTBL)

                                     Copyright 1987, 2003 Broderick Data Systems

====>_____

F3=Exit      F4=Prompt   F9=Retrieve  F12=Cancel
F13=Information Assistant  F16=System main menu
```

Remote Writer Control Options

Options 1 and 2 will start and stop a remote writer. The remote writer must be created prior to being started. For more information refer to Chapter 5, "Controlling Remote Writers".

Option 3 displays status information such as the Outq which the Remote Writer is monitoring for each active Remote Writer. For more information refer to Chapter 5, "Controlling Remote Writers".

REMOTE SPOOLPRINT3X/400™

Options 4 and 5 will start and stop the TCP Server. The TCP/IP server must be started to receive spool entries from other AS/400s using TCP/IP. For more information, refer to Appendix I, "TCP Considerations".

Remote Writer Definition Options

Options 11 and 12 are used to maintain remote writers. A remote writer must be defined for each printer on each target system which is to receive output from this system. For more information refer to Chapter 4, "Maintaining Remote Writers".

Option 13 is used to change package overall options. For more information refer to Appendix B, "Remote SpoolPrint/3X Additional Functions".

Translation Table Management Options

Options 21 thru 26 allow the user to define how certain spool file attributes will be translated during transmission. For example the user can have the AS/400 Forms ID *STD translated to 0001 when sent to a S/36. Forms ID, Font ID, and FCB ID can be translated using these options. For more information refer to Chapter 7, "Changing Forms, Font, or FCB during Transmission".

Other Commands

Options 31 thru 32 allow the AS/400 to download a file which contains a S/36 library or folder image. Refer to Appendix A, "Upload and Download Utilities" for more information. Option 33 (AS/400 only) allows the user to query the Remote SpoolPrint Log. For more information refer to Appendix B, "Additional Functions".