

# REMOTE SPOOLPRINT/36 MAIN MENU

To display the Remote SpoolPrint36 main menu, enter the following command at the command line:

**MENU RSMAIN,BDSLIB**

Then press Enter, and the following screen should appear:

```
MENU: RSMAIN

1. Start Remote Writer (STRMWTR)      13. Manage Rmt Writers (MNGRMWTR)
2. Cancel Remote Writer (CNLRMWTR)   14. List Rmt Writers (LSTRMWTR)
3. Display Rmt Status (DSPRMSTS)     15.
4. Upload a Libr to S38 (S38UPLB)    16. Manage Forms Table (MNGRMFCT)
5. Upload a Fldr to S38 (S38UPFD)    17. List Forms Table (LSTRMFCT)
6. Display RSPL Log (DSPRSLOG)       18. Manage Font Table (MNGFONT)
7. Display ICF Subsystems (D I)      19. List Font Table (LSTFONT)
8. Display APPC Groups (D A)         20. Manage FCB Table (MNGFCB)
9. Display Users (D U)               21. List FCB Table (LSTFCB)
10. Display Printer (D P)            22.
11.                                  23.
12.                                  24.

Ready for option number or command
```

## *Remote Writer Control Options*

Options 1 and 2 will start and stop a remote writer. The remote writer must be created prior to being started. Option 3 will display the status of active Remote Writers. For more information refer to Chapter 9, "Controlling Remote Writers".

Options 4 and 5 will transfer a library or folder to a remote System/38. For more information regarding the object distribution refer to Appendix A, "Remote SpoolPrint3X/400 Object Distribution".

Option 6 will allow users to query the Remote SpoolPrint Log. Refer to Appendix B, "Additional Functions" for more information.

## *Remote Writer Definition Options*

Options 13 and 14 are used to maintain remote writers. A remote writer must be defined for each printer on each target system which is to receive output from this Source System/36. For more information concerning defining Remote Writers, refer to Chapter 10, "Maintaining Remote Writers".

# **REMOTE SPOOLPRINT 3X/400™**

## ***Translation Table Options***

Options 16 thru 21 maintain translation tables which allow the Form, Font and S/370 FCB translation to take place. For more information refer to Chapter 11, "Forms, Font, and S/370 FCB Translation".

## ***SSP Commands***

Options 7 through 10 provide access to SSP commands as a convenience to the user.